


# LimagitoX File Mover *INTRO*

v20181103



LimagitoX File Mover (v2017 and up) now consists out of 5 executables:

1. LimagitoXA.exe: **A**pplication version
2. LimagitoXS.exe: **S**ervice version
3. LimagitoXC.exe: **C**onfiguration Tool
4. LimagitoXR.exe: **R**emote Setup Tool
5. LimagitoXW.exe: **W**eb Remote Service

Important: Please do not rename any of these files.

# LimagitoX File Mover *INTRO*

v20181103



## Application Version

```
(x86) LimagitoX Application v2018.0.0.0 (Memleak Mode), Corporate+ License Owner: support@l...
Tools Help Remote Setup
Log
Application Log
28/01/2018 19:40:39 Application Engine Ready
28/01/2018 19:40:39 Service state OK
28/01/2018 19:40:39 Checking service state..
28/01/2018 19:40:39 [ License Info ]
28/01/2018 19:40:39 -
28/01/2018 19:40:39 Last version you can use with the current license
is v2018.15.8.0
28/01/2018 19:40:39 -
28/01/2018 19:40:39 License Type: Corporate+ License
28/01/2018 19:40:39 License Holder: support@limagito.com
28/01/2018 19:40:39 -
28/01/2018 19:40:39 +PLUS Option Pack enabled
28/01/2018 19:40:39 -
28/01/2018 19:40:39 Started Timers
28/01/2018 19:40:39 Started IPC Server
28/01/2018 19:40:39 Started IMC Server @ 0.0.0.0:10612
```

The “Application” version no longer has a full GUI like it did in all its previous versions. A basic log window will give you some information what the application is doing. Application will mostly run at startup and minimized to the system tray. The application is the engine doing all the file transfer “work”. The setup of the application is done by a separate tool LimagitoX Remote. Click Remote Setup in the top menu to open this tool.




## Service Version

The Service version of our File Mover is an alternative for the application engine. Don’t use them both at the same time, it’s either Application or Service. Please use our “Configuration Tool” to Install/Uninstall or Stop/Start the “Service” version. Setup of the Service is now done directly by a new tool we developed, called LimagitoX Remote.



## Configuration Tool



Usage of the "Configuration" Tool:

- Service Version
  - Install/Uninstall the File Mover Service
  - Start/Stop the File Mover Service
  - Add the File Mover Service to the Windows Firewall Exception List
  - Check the Status of the File Mover Service
  - Open Windows Services.msc

# *LimagitoX File Mover* INTRO

v20181103

Usage of the "Configuration" Tool:

- Application & Service Version
  - Import License File
  - Import License Code (+PLUS Option Pack, only usable for previous Corporate License holders)
  - IPC/IMC Connection Setup
  - Install/Uninstall the Web Remote Service
  - Start/Stop the Web Remote Service
  - Add the Web Remote Service to the Windows Firewall Exception List
  - Backup Settings (SQLite DB)
  - Enable User Accounts option


# LimagitoX File Mover *INTRO*

v20181103




## Remote Tool

The setup of the application or service is done by this new tool.



At startup you'll be asked to select the destination (Application or Service):



# LimagitoX File Mover *INTRO*

v20181103

## First Usage

First you need to decide if you are going to use our File Mover as Application or Service.

### **You are going to use our File Mover as Service**

1. Install the latest version (v2018 or higher)
  - <http://limagito.com/file-mover-downloads/>
  - After installation please read the Intro.pdf file
2. Start the LimagitoX File Mover Config tool
  - Import the new License using the <Import> function (License File tab of the Config tool)
  - Click <Install> (Service tab of the Config tool). Don't start the Service yet!
  - Open Services.msc
    - Search for LimagitoX service
    - Change the 'logon as' user to a user with sufficient rights!
    - Close Services.msc
  - Click <Add 2 Firewall> (Service Tab of the Config tool)
  - Click <Start> (Service Tab of the Config tool)
  - Close Config Tool
  - The running Service is the engine doing all the file transfers.
3. Start LimagitoX File Mover Remote tool
  - Select destination: 'LimagitoX Service'
  - Click <Connect> and <OK>
4. You are now remotely connected to the service.
  - All Setup is done using this Remote tool
  - You can close the Remote tool when you are finished (it does not need to run).
5. Done

# *LimagitoX File Mover* INTRO

v20181103

## **You are going to use our File Mover as Application**

1. Install the latest version (v2018 or higher)
  - <http://limagito.com/file-mover-downloads/>
  - After installation please read the Intro.pdf file
2. Start the LimagitoX File Mover Config tool
  - Import the new License using the <Import> function (License File tab of the Config tool)
  - Close Config tool
3. Start LimagitoX File Mover Application
  - You'll notice that the Application has a basic GUI.
  - This Application is the 'Engine' and should always run. It will be doing all the file transfers.
  - There is an option to let it run minimized in the System Tray.
4. Start LimagitoX File Mover Remote tool
  - Select destination: 'LimagitoX Application'
  - Click <Connect> and <OK>
5. You are now remotely connected to the File Mover Application.
  - All Setup is done using this Remote tool
  - You can close the Remote tool when you are finished (it does not need to run)
6. Done

*Credits: [www.iconarchive.com](http://www.iconarchive.com)*